

ntp is the Network Time Protocol suite.

## Installing ntpd

First, make sure ntp/ntpdate are installed. The package is by default installed on Mandrake Linux and Redhat. If you do not have ntp installed you will find packages on your distributions install-cd(s).

On Gentoo Linux, install by typing--- emerge ntp

## Configuration files for running ntp as daemon

ntpd manpage

### Client Setup

Now, edit the following files:

--- /etc/ntp.conf

The only important thing is that the line contains server some.thing.org.

Example:

---server ntp.uio.no driftfile /etc/ntp/drift broadcastdelay 0.008 authenticate no---

Make sure you add ntpd as a boot (init) service.

Gentoo Linux: `rc-update add ntpd default` , `/etc/init.d/ntpd start`

### (LAN) Server setup

To run a ntp server to sync the clocks on your lan, edit

--- /etc/ntp.conf

Example:

---server fartein.ifi.uio.no prefer server ntp.uio.no server ntp.eunet.no

fudge 10.0.0.50 stratum 10

driftfile /etc/ntp/drift broadcastdelay 0.008

authenticate no---

fudge tells the server to pass on the correct time to the given network interface. stratum is the level of time servers, 10 being the lowest. You only need a higher number if you will be acting as a public internet timeserver with fast bandwidth.

It makes sense to add a few servers. Select the best as prefer

Make sure you add ntpd as a boot (init) service.

Gentoo Linux: `rc-update add ntpd default` , `/etc/init.d/ntpd start`

### Firewalls

ntp uses port 123, both UDP and TCP. Make sure this port is not blocked by a firewall.

If you are using iptables, you can open this port with

--- \$IPTABLES -A INPUT -j ACCEPT -p tcp --dport 123

### Known valid and working ntp servers

server address Location ntp.ipv6.viagenie.qc.ca IPv6 ONLY clock.via.netserver

fartein.ifi.uio.no Norwayserver ntp.uio.no Norwayserver

## Server List

\* <http://www.eecis.udel.edu/~mills/ntp/servers.html>

## Setting the clock at boot or using cron

A good idea is not to run the ntpd daemon on clients as it uses about 1,7 MB memory, unless you are a server or have a box with a broken clock. Many boxes clocks do drift along on their own, a check every hour or day is generally a good idea.

### rdate

rdate is a simple 3 kB tool for syncing the system clock to a server. It's options are `-p` to print the date on the given server, `-s` to set the system clock according to it (must be done as root) and `-u` to use the UDP protocol. Example:

```
`rdate -p sntp.lth.se`
```

rdate manual page

### clockspeed

clockspeed is a very small tool for setting the clock and is, for clients, a much better alternative than installing the 4+ MB ntp package.

\* [clockspeed-0.62.tar.gz](#) 28K

## cron & ntp

You can simply add ntpdate as a cron job every now and then:

```
--- echo 'ntpdate -b server.dot.com' > /etc/cron.hourly/time.cron--- chmod a+x  
/etc/cron.hourly/time.cron
```

Most distributions come with a cron. dcron and Vixie cron are nice.

## Gentoo & ntp-client

You can set the clock using ntp at boot (without starting the daemon) on Gentoo Linux by editing:

```
--- /etc/conf.d/ntp-client
```

The file should contain:

```
---NTPDATE_CMD="ntpdate"NTPDATE_OPTS="-b your.server.here"---
```

Then add ntp-client to the services started at boot:

```
--- rc-update add ntp-client default
```

You can check what services are started at boot with ``rc-status``.

Page source:

\* [t2t:ntp.t2t.tar.bz2](#)

Copyright (c) 2000-2004 Øyvind Sæther. Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.2 or any later version published by the Free Software Foundation; with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts. A copy of the license is included in the section entitled "GNU Free Documentation License".

rate this article:

current rating:

Your rating:

image:rdf newsfeed / //static.linuxhowtos.org/data/rdf.png (null)

|

image:rss newsfeed / //static.linuxhowtos.org/data/rss.png (null)

|

image:Atom newsfeed / //static.linuxhowtos.org/data/atom.png (null)

- Powered by

image:LeopardCMS / //static.linuxhowtos.org/data/leopardcms.png (null)

- Running on

image:Gentoo / //static.linuxhowtos.org/data/gentoo.png (null)

-

Copyright 2004-2020 Sascha Nitsch Unternehmensberatung GmbH

image:Valid XHTML1.1 / //static.linuxhowtos.org/data/xhtml1.png (null)

:

image:Valid CSS / //static.linuxhowtos.org/data/css.png (null)

:

image:buttonmaker / //static.linuxhowtos.org/data/buttonmaker.png (null)

- Level Triple-A Conformance to Web Content Accessibility Guidelines 1.0 -

- Copyright and legal notices -

Time to create this page: ms

<!--

image:system status display / /status/output.jpg (null)

-->